



WireGuard

cryptokey routing table with modern cryptography

tsaimh (2024, 2026)

? (?-2023)

Introduction

- WireGuard is a **communication protocol** and **free and open-source** software that implements encrypted VPNs, and was designed with the goals of **ease of use**, **high speed performance**, and **low attack surface**.
- It aims to be smaller and **better performing** than **IPsec** and **OpenVPN**.
- The WireGuard protocol passes traffic over **UDP**.
- Initially released by **Jason A. Donenfeld** for the **Linux kernel** in **2015**, it is **now cross-platform (Windows, macOS, BSD, iOS, Android)** and widely deployable.



Jason A. Donenfeld
President of
EdgeSecurity

Introduction (cont.)

- Simple and fast VPN solution
 - ✓ Low overhead
 - ✓ Deep integration with Linux kernel
 - ✓ Over UDP
- Peer to Peer
- Secure
- Built-in Roaming
 - ✓ Connections keep alive even if the underlay network change

Installation

- <https://www.wireguard.com/install/>
- Linux (kernel ≥ 3.10)
 - ✓ `sudo apt install wireguard`
- FreeBSD (13.0 or later)
 - ✓ `$ pkg install wireguard`

Tools

- Tools provided by WireGuard
 - ✓ wg
set and retrieve configuration of WireGuard interface
 - ✓ wg-quick
set up a WireGuard interface simply
- System tools
 - ✓ ip / ifconfig
setup wg interfaces
 - ✓ systemd
auto start after boot

Setup by hand (Linux)

- Add interface
 - ✓ `$ ip link add dev wg0 type wireguard`
- Setup IP address
 - ✓ `$ ip address add dev wg0 192.168.2.1/24`
 - ✓ `$ ip address add dev wg0 192.168.2.1 peer 192.168.2.2`
- Setup wg configurations
 - ✓ `$ wg setconf wg0 myconfig.conf`
 - ✓ `$ wg set wg0 listen-port 51820 private-key /path/to/private-key peer ABCDEF... allowed-ips 192.168.88.0/24 endpoint 209.202.254.14:8172`
- Setup interface
 - ✓ `$ ip link set up dev wg0`

Setup by configuration

- Configuration file
 - ✓ `/etc/wireguard/wg0.conf`
- Enable and start interface
 - ✓ `$ systemctl enable wg-quick@wg0`
 - ✓ `$ wg-quick up wg0`

Example Configurations – Client

[Interface]

Address = 10.113.0.4/16

PrivateKey = [CLIENT PRIVATE KEY]

[Peer]

PublicKey = [SERVER PUBLICKEY]

AllowedIPs = 10.113.0.0/16, 10.123.45.0/24, 1234:4567:89ab::/48

Endpoint = [SERVER ENDPOINT]:51820

PersistentKeepalive = 25

Example Configurations – Server

[Interface]

Address = 10.113.0.254/16

ListenPort = 51820

PrivateKey = [SERVER PRIVATE KEY]

note - substitute eth0 in the following lines to match the Internet-facing interface

PostUp = iptables -A FORWARD -i %i -j ACCEPT; iptables -t nat -A POSTROUTING -o eth0 -j MASQUERADE

PostDown = iptables -D FORWARD -i %i -j ACCEPT; iptables -t nat -D POSTROUTING -o eth0 -j MASQUERADE

[Peer]

PublicKey = [FOO's PUBLIC KEY]

PresharedKey = [PRE-SHARED KEY]

AllowedIPs = 10.113.0.1/32, 10.113.1.0/24

[Peer]

PublicKey = [BAR's PUBLIC KEY]

AllowedIPs = 10.113.0.2/32, 10.113.2.0/24

Configuration – Interface

- Address (optional)
IP address and netmask of the interface
- ListenPort
Wg service listen port
- PrivateKey
Private key of the interface
- PreUp / PreDown / PostUp / PostDown
Run shell scripts before / after interface up / down
(E.g. Setup firewall rules)

Configuration – Peer

- **PublicKey**
Public key of the peer
- **AllowedIPs**
IP addresses that are allowed to pass through this peer
- **Endpoint (Optional)**
Location of the peer
Wg will also use the previous connections to detect this configuration
- **PersistentKeepalive (Optional)**
By default, Wg send packs only if there are data to be send
Send packs to peer periodically to bypass NAT or Firewall
- **PresharedKey (Optional)**
Pre-shared key for additional symmetric encryption

Generate Key Pair

- Key pair
 - ✓ `$ wg genkey > privatekey`
 - ✓ `$ wg pubkey < privatekey > publickey`
- Pre-shared key
 - ✓ `$ wg genpsk > preshared`

Cryptokey Routing

- WireGuard will add routing rules to system routing table according to the configurations.
- Once packets go inside WireGuard, it is routed according to Cryptokey Routing.
 - ✓ When **sending packets**, the list of **allowed IPs** behaves as a sort of **routing table**
 - ✓ When **receiving packets**, the list of **allowed IPs** behaves as a sort of **access control list**

Built-in Roaming

- When the **client connects to server**, server record the IP of client, and communicate with client by this IP.
- When **client (or even server) change its IP**, it sends data to the peer and the **peer will update the IP**.
- Both client and server send encrypted data to the **most recent IP endpoint** for which they authentically decrypted data. Thus, there is full IP roaming on both ends.

Example – Build a Bridge VPN Server

- Follow the setup guide and build a Wg peer as a VPN server
- Enable ip forwarding
 - ✓ `sysctl net.ipv4.ip_forward=1`
- Setup NAT so clients can connect to internet through the VPN server
 - ✓ Add these lines to `wg0.conf`
 - `PostUp = iptables -A FORWARD -i %i -j ACCEPT; iptables -t nat -A POSTROUTING -o eth0 -j MASQUERADE`
 - `PostDown = iptables -D FORWARD -i %i -j ACCEPT; iptables -t nat -D POSTROUTING -o eth0 -j MASQUERADE`

Connect from mobile


- For mobile app, user can use QR-Code to import configuration file, instead of copy-paste private key from other ways
 - ✓ `$ qrencode -t ansiutf8 < wgconfig.conf`

User authentication

- Every peer has its own **private key** for **identity authentication**
- **Integration with other authentication system (like LDAP) may need other software support**
 - ✓ For now, WireGuard only provide **simple tunnel connections between peers.**

Side by Side Configuration

Source: <https://www.wireguard.com/quickstart/>



Reference

- <https://www.wireguard.com/>
- <https://www.wireguard.com/quickstart/>
- <https://www.wireguard.com/papers/wireguard.pdf>
- <https://www.zenarmor.com/docs/network-security-tutorials/how-to-install-wireguard-on-freebsd>
- <https://wiki.archlinux.org/index.php/WireGuard>